

# Sony CNA 1 Driver 1.0.0.1

---

*Atos IT Services 2017. Proprietary and Confidential*

*Original developer - Cristian Recoseanu*

## Publication Information

All materials in this document are confidential or proprietary to Atos IT Services. It is meant solely for use by the intended recipient or recipients. Any review, reliance or distribution of such material by others, or forwarding of such material without express permission is strictly prohibited.

## Overview

---

The `sony_cna1_driver` aims to enable control of the following features exposed by a Sony CNA1 device:

- Assigning CCUs to RCPs
- Getting the status of CCUs and RCPs
- Controlling CCU parameters for a particular CCU

## Table of contents

---

1. [Setting up](#)
  1. [Set up the instance](#)
  2. [Devicetypes and configuration](#)
  3. [Debug configuration](#)
2. [Running up](#)
3. [User interface](#)

## 1. Setting up

### 1.1. Set up the instance

The instance is a composite instance with the following group types:

- `cna_1` (for status information regarding the CNA1 device)
- `rcp_` (RCP number to be controlled)
- `cam_` (CCU number to be controlled)

Note: The instances needs to have the following extra attributes:

- `device_ip` - The ip address of the CNA1 device
- `device_port` - The port of the CNA1 device

Example

```

<instance composite="yes" id="cna_1_driver_mdf_1" type="cna_1_driver"
device_ip="192.168.1.27" device_port="7800" alt_id="Sony CNA 1 Driver MDF 1">
    <group id="cna_1" instance="cna_1" />
    <group id="rcp_01" instance="cna_1/rcp/01" />
    <group id="rcp_02" instance="cna_1/rcp/02" />
    <group id="rcp_03" instance="cna_1/rcp/03" />
    <group id="rcp_04" instance="cna_1/rcp/04" />
    <group id="rcp_05" instance="cna_1/rcp/05" />
    <group id="rcp_06" instance="cna_1/rcp/06" />
    <group id="rcp_07" instance="cna_1/rcp/07" />
    <group id="rcp_08" instance="cna_1/rcp/08" />
    <group id="rcp_09" instance="cna_1/rcp/09" />
    <group id="rcp_10" instance="cna_1/rcp/10" />
    <group id="rcp_11" instance="cna_1/rcp/11" />
    <group id="rcp_12" instance="cna_1/rcp/12" />
    <group id="rcp_13" instance="cna_1/rcp/13" />
    <group id="rcp_14" instance="cna_1/rcp/14" />
    <group id="rcp_15" instance="cna_1/rcp/15" />
    <group id="rcp_16" instance="cna_1/rcp/16" />
    <group id="rcp_17" instance="cna_1/rcp/17" />
    <group id="rcp_18" instance="cna_1/rcp/18" />
    <group id="rcp_19" instance="cna_1/rcp/19" />
    <group id="rcp_20" instance="cna_1/rcp/20" />
    <group id="cam_01" instance="cna_1/cam/01" />
    <group id="cam_02" instance="cna_1/cam/02" />
    <group id="cam_03" instance="cna_1/cam/03" />
    <group id="cam_04" instance="cna_1/cam/04" />
    <group id="cam_05" instance="cna_1/cam/05" />
    <group id="cam_06" instance="cna_1/cam/06" />
    <group id="cam_07" instance="cna_1/cam/07" />
    <group id="cam_08" instance="cna_1/cam/08" />
    <group id="cam_09" instance="cna_1/cam/09" />
    <group id="cam_10" instance="cna_1/cam/10" />
    <group id="cam_11" instance="cna_1/cam/11" />
    <group id="cam_12" instance="cna_1/cam/12" />
    <group id="cam_13" instance="cna_1/cam/13" />
    <group id="cam_14" instance="cna_1/cam/14" />
    <group id="cam_15" instance="cna_1/cam/15" />
    <group id="cam_16" instance="cna_1/cam/16" />
    <group id="cam_17" instance="cna_1/cam/17" />
    <group id="cam_18" instance="cna_1/cam/18" />
    <group id="cam_19" instance="cna_1/cam/19" />
    <group id="cam_20" instance="cna_1/cam/20" />
</instance>

<instance composite="no" id="cna_1" type="cna_1" location=""
ref="device=23,offset=0" alt_id="Sony CNA 1" />

    <instance composite="no" id="cna_1/rcp/01" type="cna_1_rcp" location=""
ref="device=23,offset=10" rcp_num="1" alt_id="Sony CNA 1 RCP 1" />
    <instance composite="no" id="cna_1/rcp/02" type="cna_1_rcp" location=""
ref="device=23,offset=12" rcp_num="2" alt_id="Sony CNA 1 RCP 2" />
    <instance composite="no" id="cna_1/rcp/03" type="cna_1_rcp" location=""

```

```
ref="device=23,offset=14" rcp_num="3" alt_id="Sony CNA 1 RCP 3" />
    <instance composite="no" id="cna_1/rcp/04" type="cna_1_rcp" location=""
ref="device=23,offset=16" rcp_num="4" alt_id="Sony CNA 1 RCP 4" />
    <instance composite="no" id="cna_1/rcp/05" type="cna_1_rcp" location=""
ref="device=23,offset=18" rcp_num="5" alt_id="Sony CNA 1 RCP 5" />
    <instance composite="no" id="cna_1/rcp/06" type="cna_1_rcp" location=""
ref="device=23,offset=20" rcp_num="6" alt_id="Sony CNA 1 RCP 6" />
    <instance composite="no" id="cna_1/rcp/07" type="cna_1_rcp" location=""
ref="device=23,offset=22" rcp_num="7" alt_id="Sony CNA 1 RCP 7" />
    <instance composite="no" id="cna_1/rcp/08" type="cna_1_rcp" location=""
ref="device=23,offset=24" rcp_num="8" alt_id="Sony CNA 1 RCP 8" />
    <instance composite="no" id="cna_1/rcp/09" type="cna_1_rcp" location=""
ref="device=23,offset=26" rcp_num="9" alt_id="Sony CNA 1 RCP 9" />
    <instance composite="no" id="cna_1/rcp/10" type="cna_1_rcp" location=""
ref="device=23,offset=28" rcp_num="10" alt_id="Sony CNA 1 RCP 10" />
    <instance composite="no" id="cna_1/rcp/11" type="cna_1_rcp" location=""
ref="device=23,offset=30" rcp_num="11" alt_id="Sony CNA 1 RCP 11" />
    <instance composite="no" id="cna_1/rcp/12" type="cna_1_rcp" location=""
ref="device=23,offset=32" rcp_num="12" alt_id="Sony CNA 1 RCP 12" />
    <instance composite="no" id="cna_1/rcp/13" type="cna_1_rcp" location=""
ref="device=23,offset=34" rcp_num="13" alt_id="Sony CNA 1 RCP 13" />
    <instance composite="no" id="cna_1/rcp/14" type="cna_1_rcp" location=""
ref="device=23,offset=36" rcp_num="14" alt_id="Sony CNA 1 RCP 14" />
    <instance composite="no" id="cna_1/rcp/15" type="cna_1_rcp" location=""
ref="device=23,offset=38" rcp_num="15" alt_id="Sony CNA 1 RCP 15" />
    <instance composite="no" id="cna_1/rcp/16" type="cna_1_rcp" location=""
ref="device=23,offset=40" rcp_num="16" alt_id="Sony CNA 1 RCP 16" />
    <instance composite="no" id="cna_1/rcp/17" type="cna_1_rcp" location=""
ref="device=23,offset=42" rcp_num="17" alt_id="Sony CNA 1 RCP 17" />
    <instance composite="no" id="cna_1/rcp/18" type="cna_1_rcp" location=""
ref="device=23,offset=44" rcp_num="18" alt_id="Sony CNA 1 RCP 18" />
    <instance composite="no" id="cna_1/rcp/19" type="cna_1_rcp" location=""
ref="device=23,offset=46" rcp_num="19" alt_id="Sony CNA 1 RCP 19" />
    <instance composite="no" id="cna_1/rcp/20" type="cna_1_rcp" location=""
ref="device=23,offset=48" rcp_num="20" alt_id="Sony CNA 1 RCP 20" />

    <instance composite="no" id="cna_1/cam/01" type="cna_1_camera" location=""
ref="device=24,offset=0" ccu_num="1" alt_id="Sony CAM 1" />
    <instance composite="no" id="cna_1/cam/02" type="cna_1_camera" location=""
ref="device=24,offset=100" ccu_num="2" alt_id="Sony CAM 2" />
    <instance composite="no" id="cna_1/cam/03" type="cna_1_camera" location=""
ref="device=24,offset=200" ccu_num="3" alt_id="Sony CAM 3" />
    <instance composite="no" id="cna_1/cam/04" type="cna_1_camera" location=""
ref="device=24,offset=300" ccu_num="4" alt_id="Sony CAM 4" />
    <instance composite="no" id="cna_1/cam/05" type="cna_1_camera" location=""
ref="device=24,offset=400" ccu_num="5" alt_id="Sony CAM 5" />
    <instance composite="no" id="cna_1/cam/06" type="cna_1_camera" location=""
ref="device=24,offset=500" ccu_num="6" alt_id="Sony CAM 6" />
    <instance composite="no" id="cna_1/cam/07" type="cna_1_camera" location=""
ref="device=24,offset=600" ccu_num="7" alt_id="Sony CAM 7" />
    <instance composite="no" id="cna_1/cam/08" type="cna_1_camera" location=""
ref="device=24,offset=700" ccu_num="8" alt_id="Sony CAM 8" />
    <instance composite="no" id="cna_1/cam/09" type="cna_1_camera" location=""
ref="device=24,offset=800" ccu_num="9" alt_id="Sony CAM 9" />
```

```

    <instance composite="no" id="cna_1/cam/10" type="cna_1_camera" location=""
ref="device=24,offset=900" ccu_num="10" alt_id="Sony CAM 10" />
    <instance composite="no" id="cna_1/cam/11" type="cna_1_camera" location=""
ref="device=24,offset=1000" ccu_num="11" alt_id="Sony CAM 11" />
    <instance composite="no" id="cna_1/cam/12" type="cna_1_camera" location=""
ref="device=24,offset=1100" ccu_num="12" alt_id="Sony CAM 12" />
    <instance composite="no" id="cna_1/cam/13" type="cna_1_camera" location=""
ref="device=24,offset=1200" ccu_num="13" alt_id="Sony CAM 13" />
    <instance composite="no" id="cna_1/cam/14" type="cna_1_camera" location=""
ref="device=24,offset=1300" ccu_num="14" alt_id="Sony CAM 14" />
    <instance composite="no" id="cna_1/cam/15" type="cna_1_camera" location=""
ref="device=24,offset=1400" ccu_num="15" alt_id="Sony CAM 15" />
    <instance composite="no" id="cna_1/cam/16" type="cna_1_camera" location=""
ref="device=24,offset=1500" ccu_num="16" alt_id="Sony CAM 16" />
    <instance composite="no" id="cna_1/cam/17" type="cna_1_camera" location=""
ref="device=24,offset=1600" ccu_num="17" alt_id="Sony CAM 17" />
    <instance composite="no" id="cna_1/cam/18" type="cna_1_camera" location=""
ref="device=24,offset=1700" ccu_num="18" alt_id="Sony CAM 18" />
    <instance composite="no" id="cna_1/cam/19" type="cna_1_camera" location=""
ref="device=24,offset=1800" ccu_num="19" alt_id="Sony CAM 19" />
    <instance composite="no" id="cna_1/cam/20" type="cna_1_camera" location=""
ref="device=24,offset=1900" ccu_num="20" alt_id="Sony CAM 20" />

```

## 1.2. Device types and configuration

The required devicetypes need to be present in `BNCs\your_system\config\devicetypes`.

The following devicetypes are required for complete functionality:

- cna\_1.xml
- cna\_1\_camera.xml
- cna\_1\_rcp.xml

Note: Slot allocations are read by the driver from the specific devicetype. Changing the slots in the devicetype will change where that specific parameter is presented in the infodriver.

The `sscp_iris_mapping_function.xml` file also needs to be present in `BNCs\your_system\config`.

### cna\_1.xml

This device type exposes parameters from the connected CNA1 device.

Example

```

<?xml version="1.0" encoding="UTF-8"?>
<device_description xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
name="cna_1">
    <param name="Active CNA-1" slot="1" access="readonly" style="label"
class="string" description="Active CNA-1 Device No">
    </param>
</device_description>

```

## cna\_1\_camera.xml

This device type exposes parameters from a specific CCU exposed by the connected CNA1.

### Example

```

<?xml version="1.0" encoding="UTF-8"?>
<device_description xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
name="cna_1_camera">
    <param class="enum" access="readonly" style="button" name="status"
slot="1" >
        <state value="Available" caption="Available"/>
        <state value="NotAvailable" caption="NotAvailable"/>
    </param>

    <param name="rcps_list" class="string" style="label" slot="2"
access="readonly">
    </param>

    <param name="Master Black" msg="Master Black" class="range" style="button"
subclass="integer" slot="3" slotWithOffset="0" access="readwrite">
        <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
        <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

    <param name="Black Red" msg="Black Red" class="range" style="button"
subclass="integer" slot="4" slotWithOffset="0" access="readwrite">
        <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
        <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

    <param name="Black Green" msg="Black Green" class="range" style="button"
subclass="integer" slot="5" slotWithOffset="0" access="readwrite">
        <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
        <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

    <param name="Black Blue" msg="Black Blue" class="range" style="button"
subclass="integer" slot="6" slotWithOffset="0" access="readwrite">
        <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
        <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

```

```

    <param name="White Red" msg="White Red" class="range" style="button"
subclass="integer" slot="7" slotWithOffset="0" access="readwrite">
    <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
    <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

```

```

    <param name="White Green" msg="White Green" class="range" style="button"
subclass="integer" slot="8" slotWithOffset="0" access="readwrite">
    <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
    <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

```

```

    <param name="White Blue" msg="White Blue" class="range" style="button"
subclass="integer" slot="9" slotWithOffset="0" access="readwrite">
    <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
    <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

```

```

    <param name="Saturation" msg="Saturation" class="range" style="button"
subclass="integer" slot="10" slotWithOffset="0" access="readwrite">
    <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
    <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

```

```

    <param name="Detail" msg="Detail" class="range" style="button"
subclass="integer" slot="11" slotWithOffset="0" access="readwrite">
    <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
    <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

```

```

    <param name="Master Knee" msg="Master Knee" class="range" style="button"
subclass="integer" slot="12" slotWithOffset="0" access="readwrite">
    <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
    <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

```

```

    <param name="Master Gamma" msg="Master Gamma" class="range" style="button"
subclass="integer" slot="13" slotWithOffset="0" access="readwrite">
    <values min="-99" max="99" defaultvalue="0" step="1" units="db"
value="0"/>
    <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />

```

```

    </param>

    <param name="Iris" msg="Iris" class="range" style="button"
subclass="integer" slot="14" slotWithOffset="0" access="readwrite">
        <values min="0" max="28300" defaultvalue="0" step="1" units="db"
value="0"/>
        <display inoffset="0" units="ln" outoffset="0" dp=""
multiplier="1" />
    </param>

    <param class="enum" access="writeonly" style="button" name="Auto White
Balance" slot="15" >
        <state caption="Start" value="1" style="" msg="Start" />
        <state caption="Idle" value="0" style="" msg="Idle" />
    </param>

    <param class="enum" access="writeonly" style="button" name="Auto Black
Balance" slot="16" >
        <state caption="Start" value="1" style="" msg="Start" />
        <state caption="Idle" value="0" style="" msg="Idle" />
    </param>

    <param name="Shutter" msg="Shutter" class="enum" style="button" slot="17"
access="readwrite">
        <state value="0" caption="1/60"/>
        <state value="1" caption="1/100"/>
        <state value="2" caption="1/125"/>
        <state value="3" caption="1/250"/>
        <state value="4" caption="1/500"/>
        <state value="5" caption="1/1000"/>
        <state value="6" caption="1/2000"/>
        <state value="7" caption="1/3000"/>
        <state value="8" caption="1/4000"/>
        <state value="9" caption="1/5000"/>
        <state value="10" caption="1/10000"/>
        <state value="11" caption="1/32"/>
        <state value="12" caption="1/33"/>
        <state value="13" caption="1/40"/>
        <state value="14" caption="1/48"/>
        <state value="15" caption="1/50"/>
        <state value="16" caption="1/96"/>
        <state value="17" caption="1/120"/>
    </param>

    <param name="Scene recall" msg="Shutter" class="enum" style="button"
slot="18" access="readwrite">
        <state value="1" caption="Scene 1"/>
        <state value="2" caption="Scene 2"/>
        <state value="3" caption="Scene 3"/>
        <state value="4" caption="Scene 4"/>
        <state value="5" caption="Scene 5"/>
    </param>

    <param name="Scene store" msg="Shutter" class="enum" style="button"

```



```

slot="19" access="readwrite">
    <state value="1" caption="Scene 1"/>
    <state value="2" caption="Scene 2"/>
    <state value="3" caption="Scene 3"/>
    <state value="4" caption="Scene 4"/>
    <state value="5" caption="Scene 5"/>
</param>
</device_description>

```

### cna\_1\_rcp.xml

This device type exposes parameters from a specific RCP exposed by the connected CNA1.

Example

```

<?xml version="1.0" encoding="UTF-8"?>
<device_description xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
name="cna_1_rcp">
    <param class="enum" access="readonly" style="button" name="status"
slot="1" >
        <state value="Available" caption="Available"/>
        <state value="NotAvailable" caption="NotAvailable"/>
    </param>

    <param name="camera" slot="2" access="readwrite" style="label"
class="string" description="RCP Camera">
    </param>
</device_description>

```

### sscp\_iris\_mapping\_function.xml

This file maps the values obtained from the CNA to fStop numbers

Example

```

<?xml version="1.0" encoding="utf-8"?>
<items>
    <item value="1.8" min="28128" max="28300" />
    <item value="1.9" min="27776" max="28127" />
    <item value="2.0" min="27456" max="27775" />
    <item value="2.1" min="27136" max="27455" />
    <item value="2.2" min="26848" max="27135" />
    <item value="2.3" min="26560" max="26847" />
    <item value="2.4" min="26304" max="26559" />
    .....
    <item value="22.0" min="11840" max="11871" />
    <item value="22.1" min="11808" max="11839" />
    <item value="22.2" min="11776" max="11807" />

```



```
<item value="22.3" min="11744" max="11775" />
<item value="22.4" min="11712" max="11743" />
<item value="22.5" min="0" max="11711" />
</items>
```

### 1.3. Debug configuration

The debug configuration is stored in the "sony\_cna1\_driver.exe.nlog" in the same folder as the application executable.

This will create log files in `BNCS\your_system\Logs\sony_cna1_driver`.

Example

```
<?xml version="1.0" encoding="utf-8" ?>
<nlog xmlns="http://www.nlog-project.org/schemas/NLog.xsd"
      xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">

  <extensions>
    <add assembly="NlogViewer" />
  </extensions>
  <targets>
    <target xsi:type="NlogViewer" name="DebugWindow" />
    <target xsi:type="OutputDebugString" name="DebugView"
layout="${var:instance}|${level:uppercase=true}|${logger:shortName=false}|${message}" />
    <target xsi:type="File" name="File"
      layout="${date} :+ : ${callsite} :+ : ${message}"
      deleteOldFileOnStartup="false"

      fileName="${environment:variable=CC_ROOT}\${environment:variable=CC_SYSTEM}\logs\${processname}\${processname}_${var:instance:default=no_instance_supplied}_${date:format=yyyyMMdd-HH}.log"

      archiveFileName="${environment:variable=CC_ROOT}\${environment:variable=CC_SYSTEM}\logs\${processname}\archive\${processname}_${var:instance:default=no_instance_supplied}_{#}.log"
      archiveEvery="Hour"
      archiveNumbering="Date"
      archiveDateFormat="yyyyMMdd-HH"
      archiveOldFileOnStartup="false"
      maxArchiveFiles="168"
      keepFileOpen="true"
      encoding="iso-8859-2" />
  </targets>
  <rules>
    <logger name="*" minlevel="Trace" writeTo="DebugView" />
    <logger name="*" minlevel="Debug" writeTo="File" />
    <logger name="always" minlevel="Debug" writeTo="DebugWindow" final="true" />
    <logger name="*" minlevel="Debug" writeTo="DebugWindow" />
```

```
</rules>  
</nlog>
```

## 2.0. Running up

The application requires its instance as the argument.

Example

```
sony_cna1_driver.exe cna_1_driver_mdf_1
```

## 3.0. User interface

The following views are available on the user interface:

- CNA 1
- RCPs
- CCUs
- CCU Assignment

### CNA 1

The CNA 1 view is mainly used for debugging purposes when the driver application cannot establish a reliable connection to the CNA1.

This could happen for a number of reasons:

- No MSU unit connected
- Gateway is not enabled
- There is no CCU in the system

The driver requests via HTTP the status of the CNA 1 in order to expose more of the configuration parameters which may be causing the issue. The following fields are exposed in the **CNA 1 Info** datagrid:

- HTTP Status - whether the web server of the CNA 1 can be reached
- Device No - the device number of the CNA 1
- IP Address - the ip address of the CNA 1
- Port - the port of the CNA 1
- Gateway Enabled - if the CNA 1 has the gateway feature enabled
- Mode - the CNA 1 mode
- CNS Mode - the CNA 1 CNS Mode
- Master IP - the IP address of the master MSU device
- Bridge Con Mode - the CNA 1 bridge con mode
- Last OK Response - the last timestamp when the CNA 1 web server was reached successfully

Some of these expected states are defined in the file driver\_config.xml which must be present in the config folder of a v4.x system.

Example file:

```
<driver id="cna_1_driver_mdf_1">
  <setting id="DebugLevel" value="Normal" />
  <setting id="LogLevel" value="Normal" />
  <setting id="HttpStatus" value="OK" />
  <setting id="DeviceNo" value="91" />
  <setting id="IP_Address" value="10.161.192.125" />
  <setting id="Port" value="7800" />
  <setting id="GatewayEnabled" value="True" />
  <setting id="Mode" value="msu" />
  <setting id="CnsMode" value="mcs" />
  <setting id="MasterIP" value="10.161.192.124" />
  <setting id="BridgeConMode" value="active" />
</driver>
```

## RCPs

The RCPs view is used to indicate useful parameters for an RCP.

The following fields are exposed in the **RCPs** datagrid:

- RCP - the RCP number
- Status - the RCP status (NotAvailable or Available)
- CCU - the current assigned CCU number
- Instance - the instance associated with this RCP
- DeviceType - the devicetype associated with this RCP
- Device - the BNCS device number associated with this RCP
- Offset - the BNCS offset associated with this RCP

## CCUs

The CCUs view is used to indicate useful parameters for a CCU.

The following fields are exposed in the **Managed CCUs** datagrid:

- CCU - the CCU number
- Status - the CCU status (NotAvailable or Available)
- Instance - the instance associated with this CCU
- Label - the instance alt id associated with this CCU
- DeviceType - the devicetype associated with this CCU
- Device - the BNCS device number associated with this CCU
- Offset - the BNCS offset associated with this CCU
- Selected - whether this CCU is currently selected for polling
- RCP List - comma delimited list of current RCPs who have been assigned to this CCU

Upon selecting a row in the **Managed CCUs** datagrid the **CCU Parameters** datagrid gets targeted with the context for the selected CCU. The **CCU Parameters** datagrid exposes all of the parameters in the **cna\_1\_camera.xml** devicetype alongside their current value.

## CCU Assignment

The CCU Assignment view exposes one datagrid for CCUs and one for RCPs and allows a selected CCU to be assigned to a selected RCP. The view also has a **Clear** button in order to clear an assignment for a selected RCP.

## Version Control

Version	Date	Author	Comments
1.0	27/06/2018	Cristian Recoseanu	Initial document
1.1	30/10/2018	Andrew Prince	Added reference to sscp_iris_mapping_function.xml
1.1.1	09/01/2020	Scott Harman	Added missing parameter for RCP and CCU entries in instances.xml